

## Linux - Open Ports After Initial Installation

Port	Protocol	Service	Location
7	TCP	<a href="#">echo</a>	<a href="#">/etc/inetd.conf</a>
7	UDP	<a href="#">echo</a>	<a href="#">/etc/inetd.conf</a>
9	TCP	<a href="#">discard</a>	<a href="#">/etc/inetd.conf</a>
9	UDP	<a href="#">discard</a>	<a href="#">/etc/inetd.conf</a>
11	TCP	<a href="#">tftp</a>	<a href="#">/etc/inetd.conf</a>
13	TCP	<a href="#">daytime</a>	<a href="#">/etc/inetd.conf</a>
13	UDP	<a href="#">daytime</a>	<a href="#">/etc/inetd.conf</a>
19	TCP	<a href="#">chargen</a>	<a href="#">/etc/inetd.conf</a>
19	UDP	<a href="#">chargen</a>	<a href="#">/etc/inetd.conf</a>
21	TCP	<a href="#">ftp</a>	<a href="#">/etc/inetd.conf</a>
23	TCP	<a href="#">telnet</a>	<a href="#">/etc/inetd.conf</a>
25	TCP	<a href="#">smtp</a>	<a href="#">/etc/rc.d/rc3.d/S80sendmail</a>
37	TCP	<a href="#">time</a>	<a href="#">/etc/inetd.conf</a>
37	UDP	<a href="#">time</a>	<a href="#">/etc/inetd.conf</a>
42	UDP	<a href="#">name</a>	<a href="#">/etc/inetd.conf</a>
53	TCP	<a href="#">domain</a>	<a href="#">/etc/rc.d/rc3.d/S55named</a>
53	UDP	<a href="#">domain</a>	<a href="#">/etc/rc.d/rc3.d/S55named</a>
79	TCP	<a href="#">finger</a>	<a href="#">/etc/inetd.conf</a>
80	TCP	<a href="#">http</a>	<a href="#">/etc/rc.d/rc3.d/S85httpd</a>
98	TCP	<a href="#">linuxconf</a>	<a href="#">/etc/inetd.conf</a>
110	TCP	<a href="#">pop3</a>	
111	TCP	<a href="#">rpc</a>	<a href="#">/etc/rc2.d/S71rpc</a>
111	UDP	<a href="#">rpc</a>	<a href="#">/etc/rc2.d/S71rpc</a>
113	TCP	<a href="#">ident, auth</a>	<a href="#">/etc/inetd.conf</a>
119	TCP	<a href="#">innd</a>	<a href="#">/etc/rc.d/rc3.d/S95innd</a>
139	TCP	<a href="#">smbd</a>	<a href="#">/etc/rc.d/rc3.d/S91smb</a>
161	UDP	<a href="#">snmp</a>	<a href="#">/etc/rc3.d/S76snmpdx</a>
177	UDP	<a href="#">xdmcp</a>	<a href="#">/etc/rc2.d/S99dtlogin</a>
512	TCP	<a href="#">exec</a>	<a href="#">/etc/inetd.conf</a>
512	UDP	<a href="#">comsat</a>	<a href="#">/etc/inetd.conf</a>
513	TCP	<a href="#">login</a>	<a href="#">/etc/inetd.conf</a>
513	UDP	<a href="#">who</a>	<a href="#">/etc/rc.d/rc3.d/S60rwhod</a>
514	TCP	<a href="#">shell</a>	<a href="#">/etc/inetd.conf</a>
514	UDP	<a href="#">syslog</a>	<a href="#">/etc/rc2.d/S74syslog</a>
515	TCP	<a href="#">printer</a>	<a href="#">/etc/rc.d/rc3.d/S60lpd</a>
517	UDP	<a href="#">talk</a>	<a href="#">/etc/inetd.conf</a>
518	UDP	<a href="#">ntalk</a>	<a href="#">/etc/inetd.conf</a>
520	UDP	<a href="#">routed</a>	<a href="#">/etc/rc.d/rc2.d/S55routed</a>
540	TCP	<a href="#">uucp</a>	<a href="#">/etc/inetd.conf</a>
668-1024	TCP,UDP	<a href="#">ypbind</a>	<a href="#">/etc/rc.d/rc3.d/S13ypbind</a>
		<a href="#">nfs</a>	<a href="#">/etc/rc.d/rc3.d/S60nfs</a>